

VerboMaître 2.0

(Installation for Windows)

Single-user licence

Minimum Configuration Required:

Microsoft Windows® (2000/ME/XP/Vista), Pentium III or higher, 64 MB RAM, 800x600 / 1024x768 Graphics Card Resolution, 35 MB Free hard drive space, and CD-ROM.

Should you have any problem, please refer to the notes below.

See the last section of the FAQ for problems with Windows Vista.

Windows Installation:

1. Close any application that may be in use.
2. Insert the CD in the CD-ROM unit and follow the instructions from the Installation Wizard.

If the start-up program is not launched automatically, take the following steps:

For Windows Me / 2000

1. Click on the Windows "Start" button.
2. Choose the option "Parameters," then "Configuration Panel."
3. Double-click on the icon "Add/Remove Program."
4. Click on the tab "Install/Uninstall," then on "Install."

For Windows XP

1. Click on the Windows "Start" button.
2. Choose the option "Parameters," then "Configuration Panel."
3. Double-click on the icon "Add/Remove Program."
4. Click on the button "Add New Program."
5. Click on the button "CD-ROM or Floppy Disk."
6. Follow the instructions. The file to start the installation is "Setup.Exe."

For Windows Vista

1. Click on the Windows Vista "Start" button.
2. Choose "Computer."
3. Right click on the peripheral or player, then click on "Install or run a program."
4. Click on "Run AutoRun.exe."
5. Follow the instructions. The file to start the installation is "Setup.Exe."

Note: During installation, you will have to choose a location for the application and define user access rights (if several users have been registered in your computer). We advise you to install VerboMaître at the location suggested by the Wizard, and to tick the box "Everyone" so that all users will have access.

3. Click on the buttons "Next," and then "Close." The software is now installed.
4. Click on the software icon to launch VerboMaître. This icon appears on the desktop, or in the Windows Program Menu.

Installation of .NET Framework, version 1.1 :

During installation, you may get a message asking you to install version 1.1 of .NET Framework (Service Pack 1). This file has everything you need to run applications developed with .NET Framework.

You will find the French, English and Spanish versions of Service Pack 1 on your VerboMaître CD-ROM. You can also download them for free from the Microsoft website.

For more information on this component or on how to obtain the language version that corresponds to your computer, please visit:

<http://www.microsoft.com/downloads/details.aspx?displaylang=fr&FamilyID=A8F5654F-088E-40B2-BBDB-A83353618B38>

To install version 1.1 of the .NET Framework application from the VerboMaître CD-ROM, follow the steps below:

1. Click on the Windows "Start" button, choose Programs/Accessories, then go to "Windows Explorer."
- or

- Double-click on the icon "My Documents" or "Desktop."
2. Click on the name of the unit where the VerboMaître CD-ROM has been placed.
 3. Double-click on the folder "Service Pack 1."
 4. Click on the folder "SP1 English" if your Windows application is in English; on "SP1 French," if it is in French, or on "SP1 Spanish," if it is in Spanish.
 5. Double-click on the file "dotnetfx.exe" and follow the Wizard's instructions.
 6. Restart your computer.
 7. Resume installation as of step 2.

FAQ :

1.- Error starting VerboMaître (Windows 2000 and Me)

"The .Net data OLE DB Provider(System.Data.OleDb) requires Microsoft Data Access Components(MDAC) version 2.6 or later. Version 02.10.3711.9 was found currently installed."

This error occurs when starting the software, not during installation. We have found that certain computers equipped with Windows 98 and 2000 are missing the MDAC 2.8 library (Microsoft Data Access Component) that is required to communicate with the VerboMaître database.

Click on the Microsoft link [MDAC_TYP.EXE](#) (file name) or copy the link below and paste it in your web browser. Select the linguistic version that corresponds to your computer.

<http://www.microsoft.com/downloads/details.aspx?familyid=6c050fe3-c795-4b7d-b037-185d0506396c>

Follow the installation instructions. Once the library has been installed, reboot the computer and start VerboMaître again.

2.- Is VerboMaître 2.0 compatible with Windows Vista?

Yes, VerboMaître is 100 % compatible with Windows Vista. However, during installation, you may receive a message indicating that ".NET Framework version 1.1" must be installed. Do not follow the installation process suggested by the installer. Even if you have a more recent version of the Service Pack, VerboMaître was developed with the library version. Installing Service Pack 1.1 will not cause any conflict with the version already installed on your computer or with Windows Vista.

To install this component, follow the procedure listed under «Installation of .NET Framework, version 1.1 ».

Should you experience any other problem, please email info@aleainfo.com

© 2006-2009 **Aleatorium Informatique Inc.**

Web site: www.aleainfo.com

Montreal (Quebec) – Canada